



Mastertronic

Auto Firmware (FW) Update

Things you'll need:

1. Philips Screwdriver (+)


Why I need this update?

1. We have solved an important bug where the leak detector doesn't perform correctly. This update will solve the bug without the need to perform manual update with USB cables and PC.
2. This update will also allow future firmware update done automatically.


Instruction

1. Make sure your unit is showing with SW V01.05.01 (or later). Check from AIO app.
2. Power off unit, open the back cover.
3. Remove jumper, close back cover. Keep the jumper in safe place in case needed in future. (Refer to pic A, B, C)
4. Power on (LCD will show a blank screen for 1 min).
5. When LCD resumes to standby (Mastertronic), go to [cloud site](#).
6. Click on "Enable auto Firmware update". **SAVE**.
7. Wait for download and update.
8. Check app after 10 min and you should get FW01.03.04.



Pic A




Pic B



Pic C





FOCUSTRONIC